

--	--	--	--	--	--

[illegible]

IP

[illegible]

1. IP (117.56.68.133)
2. FQDN (odf.nat.gov.tw)

modaodfweb

```
/etc/modaodfweb/modaodfweb.xml
```

[illegible]

```
<wopi desc="Allow/deny wopi storage. Mutually exclusive with webdav." allow="true">
<host desc="Regex pattern of hostname to allow or deny." allow="true">localhost</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">10\.[0-9]{1,3}\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">172\.[16789]\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">172\.[20-9]\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">172\.[301]\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">192\.[168]\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">117\.[56\.[68\.[133</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">odf\.nat\.gov\.tw</host>
<host desc="Regex pattern of hostname to allow or deny." allow="false">192\.[168]\.[1\.[1</host>
<max_file_size desc="Maximum document size in bytes to load. 0 for unlimited."
type="uint">0</max_file_size>
</wopi>
```

117.56.68.133 odf.nat.gov.tw

modaodfweb

```
# systemctl restart modaodfweb
```

80□ 9980

TTTTTT ODF TTTTTT

(2) 設定 ODF API 環境

ODF API 環境構築 2.X 環境構築 ODF API 環境構築 ODF
modaodfweb 環境構築
/etc/modaodfweb/modaodfweb.xml 環境構築

```
<server_name desc="External hostname:port of the server running modaodfweb. If empty, it's derived from the  
request (please set it if this doesn't work). Must be specified when behind a reverse-proxy or when the hostname is  
not reachable directly." type="string" default=""></server_name>
```

</server_name>default="" ODF URL
192.168.3.1:9980 modaodfweb

```
# systemctl restart modaodfweb
```

(3) SSL 設定

SSL 環境構築 SSL 環境構築 GCA

<https://gcp.nat.gov.tw/>

modaodfweb /etc/httpd/ssl

- Apache Web Server

ssl

```
# yum install -y mod_ssl  
# vim /etc/httpd/conf.d/ssl.conf
```

```
SSLCertificateFile /etc/httpd/ssl/certificate.crt  
SSLCertificateKeyFile /etc/httpd/ssl/private.key  
SSLCACertificateFile /etc/httpd/ssl/ca_bundle.crt
```

```
# systemctl restart httpd
```

- ODF Web

modaodfweb /etc/modaodfweb/modaodfweb.xml

