

--	--	--	--	--	--

(1) 

--	--	--	--	--	--	--	--	--

**IP**

[illegible]

1.  IP  ( 117.56.68.133)
2.  FQDN  ( odf.nat.gov.tw)

modaodfweb

```
/etc/modaodfweb/modaodfweb.xml
```

[illegible]

```
<wopi desc="Allow/deny wopi storage. Mutually exclusive with webdav." allow="true">
<host desc="Regex pattern of hostname to allow or deny." allow="true">localhost</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">10\.[0-9]{1,3}\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">172.1[6789]\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">172.2[0-9]\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">172.3[01]\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">192.168\.[0-9]{1,3}\.[0-9]{1,3}</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">117\.56\.68\.133</host>
<host desc="Regex pattern of hostname to allow or deny." allow="true">odf\.nat\.gov\.tw</host>
<host desc="Regex pattern of hostname to allow or deny." allow="false">192\.168\.[0-9]{1,3}\.[0-9]{1,3}</host>
<max_file_size desc="Maximum document size in bytes to load. 0 for unlimited."
type="uint">0</max_file_size>
</wopi>
```

117.56.68.133 odf.nat.gov.tw

modaodfweb

--	--	--	--	--	--

```
# systemctl restart modaodfweb
```

80 9980

TTTTT ODF TTTTT

## (2) 安裝 ODF API 軟體

安裝 ODF API 軟體 2.X 版本 ODF API 軟體 ODF  
modaodfweb 軟體  
/etc/modaodfweb/modaodfweb.xml 軟體

```
<server_name desc="External hostname:port of the server running modaodfweb. If empty, it's derived from the  
request (please set it if this doesn't work). Must be specified when behind a reverse-proxy or when the hostname is  
not reachable directly." type="string" default=""></server_name>
```

</server\_name> <.....default=""> ODF 軟體 URL  
192.168.3.1:9980 modaodfweb  
軟體

```
# systemctl restart modaodfweb
```

## (3) 安裝 SSL 軟體

SSL 軟體 SSL 軟體 GCA  
軟體

<https://gcp.nat.gov.tw/>

modaodfweb /etc/httpd/ssl 軟體

- Apache Web Server 軟體

ssl 軟體

```
# yum install -y mod_ssl  
# vim /etc/httpd/conf.d/ssl.conf
```

軟體

```
SSLCertificateFile /etc/httpd/ssl/certificate.crt  
SSLCertificateKeyFile /etc/httpd/ssl/private.key  
SSLCACertificateFile /etc/httpd/ssl/ca_bundle.crt
```

軟體

```
# systemctl restart httpd
```

- ODF 軟體 Web 軟體

modaodfweb 軟體 /etc/modaodfweb/modaodfweb.xml 軟體

<enable type="bool" desc="Controls whether SSL encryption is enable (do not disable for production deployment). If default is false, must first be compiled with SSL support to enable." default="true">true</enable>

☐ </enable> ☐ false ☐ true

☐ httpd ☐ SSL ☐

<cert\_file\_path desc="Path to the cert file" relative="false">/etc/httpd/ssl/certificate.crt</cert\_file\_path>  
<key\_file\_path desc="Path to the key file" relative="false">/etc/httpd/ssl/private.key</key\_file\_path>  
<ca\_file\_path desc="Path to the ca file" relative="false">/etc/httpd/ssl/ca\_bundle.crt</ca\_file\_path>

☐ modaodfweb ☐

# systemctl restart modaodfweb

☐

https://yourhostname:9980 → ☐ ODF☐ Web  
☐ OK  
☐

https://yourhostname/odfweb → ☐ ODF☐ Web  
☐